

STUDENT PILOT REFERENCE GUIDE





Use with ATARI® 400™ or ATARI 800™ PERSONAL COMPUTER SYSTEMS

STUDENT PILOT Reference Guide



Every effort has been made to ensure that this manual accurately documents this product of the ATARI Computer Division. However, because of the ongoing improvement and update of the computer software and hardware, ATARI, INC. cannot guarantee the accuracy of printed material after the date of publication and cannot accept responsibility for errors or omissions.

Reproduction is forbidden without the specific written permission of ATARI, INC., Sunnyvale, CA 94086. No right to reproduce this document, nor the subject matter thereof, is granted unless by written agreement with, or written permission from the Corporation.

PRINTED IN U.S.A

PROGRAM CONTENTS © 1980 ATARI, INC. MANUAL CONTENTS © 1981 ATARI, INC.

PREFACE

PILOT is a simple, easy-to-understand programming language. It stands for Programmed Inquiry, Learning Or Teaching, and was originally developed by Dr. John Starkweather at the University of California, San Francisco. PILOT was designed to enable teachers to write programs for their students. However, due to the pioneering work of Dr. Dean Brown at Stanford Research Institute's Education Laboratory (1967-1974), PILOT proved to be a good language for teaching computer programming to children. PILOT was conceived as a tool to make writing conversational programs easy. It was originally designed for text output only. However, we have incorporated **Turtle Graphics**, a concept developed by Dr. Seymour Papert and the LOGO group at the Massachusetts Institute of Technology. The Turtle Graphics concept enables the user to draw pictures when programming in PILOT. These capabilities, along with the ability to generate sounds, make **ATARI® PILOT** a very versatile language.

TABLE OF CONTENTS

P	REFACE		iii
IN	TRODUCTION		vii
1	PILOT INFOR	NATION	1
	Terms Operating Modes		2 3
	Variables		4
	Arithmetic Operate Relational Operate	ors	4 5 5
	Error Messages	515	56
2	CORE PILOT		
-	CORE PILOT		7
	T: Type		8
	A: Accept M: Match		12 14
	J: Jump		14
	C: Compute Random N		19
	E: End	umbers	21 24
	U: Use		24
	R: Remark		30
3	EXECUTIVE C	OMMANDS	31
	AUTO	Automatic Line Numbering	32
	RUN	Run a Program	34
	LIST REN	List a Program Renumber a Program	36
	NEW	New Program	39 41
	VNEW	New Variables	43
	DUMP LOAD	Dump String Variables	46
	LOAD C:	Load a Program Loading From Cassette	48 48
	LOAD D:	Loading From Diskette	40 49
	CAUE	Merging Programs	49
	SAVE SAVE C:	Save a Program Save to Cassette	51
	SAVE D:	Save to Diskette	51 52
	SAVE P:	Save to Printer	52
	DOS	Disk Operating System	53

4 GRAPHICS

GR:	Graphics	56
	Turtle Graphics	57
	Where To $Go - X$ and Y Coordinates	57
	What Direction and How Far To Go	58
	Initial Location, Heading, and Pen Color	58
	Shortcuts for Graphics Programming	59
GR:CLEAR	Clear the Graphics Screen	60
GR:GOTO	Go to the Point X,Y	62
GR:DRAWTO	Draw to the Point X, Y	64
GR:FILLTO	Fill to the Point X,Y	66
GR:TURNTO	Turn to N Degrees	68
GR:TURN	Turn N Degrees	70
GR:GO	Go N Units	72
GR:DRAW	Draw N Units	74
GR:FILL	Fill N Units	76
GR:PEN	Choose a Pen Color	78
GR:PEN ERASE	Set Pen Color to Erase	80
GR:PEN UP	Lift the Pen	81
GR:QUIT	Quit the Graphics Mode	82
	Can une erapinee rioue	02

5 SOUND AND PAUSE

85

93

55

SO:	Sound	86
PA:	Pause N Units	89

6 CONDITIONALS

Y or N	String Match Conditions	95
COMPARISON	Numeric Conditions	98
JM:	Jump on Match	101

APPENDICES

A	SPECIAL FUNCTION KEYS AND SCREEN EDITING	103
B	PILOT I/O ERROR CODES	106



INTRODUCTION



This reference guide is designed for your use if you are learning PILOT at home or in school, or if you already know PILOT and need a handy guide to the language. It gives brief explanations of all the main PILOT commands and examples of their use. Throughout this guide there are illustrations to enhance your understanding and enjoyment of PILOT. You are the pilot character; you give PILOT commands to the computer. Anytime you are in Graphics mode, the turtle character is ready to obey your commands. Each PILOT command is highlighted in large **bold** letters at the top of a page so you can easily find any command to which you wish to refer. This reference guide is divided into the following sections: PILOT Information, Core PILOT, Executive Commands, Graphics, Sound and Pause, and Conditionals.

In the first section, you will find terms to know and general information about the PILOT language. You should be familiar with the contents of this section in order to use this guide.

The second section reviews the Core PILOT commands. You put these commands together as a set of numbered statements to form a program. You can also execute them one at a time in Immediate mode, just as you would use a pocket calculator.

The third section reviews Executive commands. These commands allow you to do various things with programs as a whole. You give executive commands directly from the keyboard; **usually** they are not part of a program.

The fourth section covers turtle Graphics commands, which you use to draw designs or pictures on the screen. When PILOT is in graphics mode, an invisible turtle, holding an invisible pen, moves around the screen following your commands, drawing lines, and filling in spaces.

The fifth section has to do with the SOUND and PAUSE commands. SOUND is most frequently used when you want to make music, but can also help you create sound for a special effect. PAUSE lets you create a dramatic effect in a program, but it is used most often when creating music; for example, when you need to indicate how long a tone is to be played.

The last section discusses Conditional commands. Any PILOT command can be made conditional; that is, it will only be carried out if certain conditions are met. This section reviews the various kinds of conditions you can set up in your programs.

This is just a reference guide. If you need further explanation of any PILOT command, or if you wish to learn PILOT from a book, you should refer to the PILOT Primer: An Instructional Manual for the PILOT Programming Language.

1 PILOT INFORMATION



This section contains general information about PILOT. It includes explanations of terms often used in this guide, PILOT operating modes, variables, arithmetic and relational operators, and error messages.

TERMS

COMMANDS	Commands tell the computer what to do. There are two kinds of commands: Program Commands and Executive Commands.
	Program Commands are the building blocks of the PILOT language. They are composed of one or two letters followed by a colon (:). When placed in a logical sequence, these commands make up a program.
	Executive Commands tell the computer what to do with a program as a whole. Executive commands are either a short word such as RUN or an abbreviation such as DOS.
CONSTANT	A constant is a value expressed as a number rather than represented by a variable name. For example, in the statement:
	C:#X = 100
	#X is a variable, and 100 is a constant.
CURSOR	The white square that moves across the television screen showing your location on the screen as you type.
EXPRESSION	An expression is any combination of variables, constants, and arithmetic or relational operators used together to compute a value. For example, $#A + #B \ 2$ is an expression; so is $#A <= #B$.
INPUT	Any information <i>put into</i> the computer from the keyboard, cassette tape, disk, and so on.
LABEL	Code name or symbols given to a statement in a program to iden- tify that statement for reference by a J: or U: command. PILOT labels may be any combination up to 254 characters. Labels must start with an asterisk (*) and a letter; for example, * HERE or * M35PDQ.
MEMORY	The part of the computer where information is stored. This infor- mation is both program statements and data (constants and variables) that the program uses when it is run.

OUTPUT Information *put out* from the computer memory to external devices.

PILOT PILOT stands for Programmed Inquiry, Learning Or Teaching.

PROGRAM A set of statements in a logical sequence that tells the computer what to do. The computer follows the program statements in order, from beginning to end, unless a J: JUMP or U: USE command breaks the sequence.

SCREEN DISPLAY What you see on the television screen.

STATEMENT A statement is one line of a program. All PILOT statements begin with line numbers (used for editing and sequencing). A PILOT statement may be labeled with a ***** LABEL between the line number and the command.

STRING A group of characters—letters, numbers, punctuation, or ATARI Graphics (CTRL) characters. The following are all strings:

> ABCXYZZZ "Quotes Too" 02BAK9 /\/\/\/\/\/ 5 + 2 =

Note that quotation marks are not used to identify a string. Any group of characters, including quotation marks, is a string in PILOT.

A string is like a constant, in that it may be stored in a string variable.

VARIABLE A variable is the name of a place in memory to store a string or numeric value that is used by a program. This value may (or may not) change as the program is executed. (See the following page for an explanation of the different types of PILOT variables.)

OPERATING MODES

PILOT has two kinds of modes: *Programming Modes* which determine how PILOT commands are used by the computer; and *Screen Modes* which determine the layout of the display screen.

	Programming Modes
AUTO	The mode in which the statements will automatically be numbered when writing a program.
IMMEDIATE	The Immediate mode is used when you want your commands to respond right away after pressing the RETURN key.
RUN	In Run mode, PILOT is executing (carrying out) the program cur- rently stored in memory.
	Screen Modes
GRAPHICS	The Graphics mode is used when you want to draw a picture of any kind.
TEXT	The Text mode displays only text (letters, numbers, punctuation) and graphics (CTRL) characters.

VARIABLES

PILOT has two main kinds of variables: string variables and numeric variables.

String Variables can store strings of up to 254 characters. They are named with a \$ symbol, followed by any combination of letters and numbers. For example, \$NAME, \$M29ABD, \$FOOD9 are acceptable string variable names. String variables *cannot* be used in arithmetic expressions. A program can contain any number of string variables up to the limits of memory.

Numeric Variables can store numbers from -32768 through 32767. They are named with a # symbol, followed by a single letter; #A, #B, #C, and so on up to #Z are the acceptable numeric variable names. A program can have up to 26 numeric variables. They can be used in arithmetic and relational expressions.

Note: PILOT has two other kinds of variables that are not discussed in this guide. Pointer variables, named with an @ symbol followed by a decimal memory location, are used to examine or change the contents of a specific memory location (equivalent to PEEK and POKE in the BASIC language). **Special** variables, named with a % symbol followed by a letter or a letter and a number, are used to sense the values of the various ATARI controllers (joysticks, paddles, and light pen) and to read other special values maintained by the PILOT system.

The use of controllers and special graphics variables is explained in *The PILOT Primer*, An Instruction Manual for the PILOT PROGRAMMING LANGUAGE. Information on the use of pointer variables and other special variables may be obtained by phoning ATARI, INC., Customer Support:

(800) 538-8547 (Outside California) (800) 672-1430 (Within California)

ARITHMETIC OPERATORS

The ATARI PILOT language uses five arithmetic operators:

- + addition
- subtraction (also denotes a negative numbers; e.g., -5)
- * multiplication
- / division
- \ modulo (the remainder after a division)

Note: PILOT only performs integer (whole numbers) arithmetic.

Parentheses () can be used to change the order in which arthmetic is performed. For example C:#A=5+6 ***** 2 puts the number 22 in variable #A; on the other hand, C:#A=5+(6 ***** 2) puts the number 17 in variable #A.

RELATIONAL OPERATORS

PILOT allows the result of the comparison between two variables or constants to be used as a condition for executing a command. The comparison is made with the use of the following relational operators:

#A < #B	#A is less than #B
#A > #B	#A is greater than #B
#A = #B	#A equals #B
#A < = #B	#A is less than or equal to #B
#A > = #B	#A is greater than or equal to #B
#A <>#B	#A is not equal to #B

(See Section 6, Conditionals.)

ERROR MESSAGES

If you make an error, PILOT responds by showing the command or statement in error. It highlights the source of the error or the first character it does not understand. It also types out a message explaining the error.

The are two kinds of errors: **Syntax errors** result from incorrectly typing in a command. Syntax errors are found by PILOT as you are typing commands or program statements into the computer.

The second type of error is a **Run-time error** which results from mistakes in the logic of your program - for example, trying to jump to a statement that you have not labeled. Run-time errors are only found when you type RUN and PILOT tries to execute your program.

The following are some common PILOT error messages:

WHAT'S THAT?	Indicates that PILOT could not understand your command or what you wanted it to do. This message is often the result of typing or spelling errors.
I/O ERROR xxx	In the course of performing an I/O operation the I/O subsystem detected an error and returned the status indicated. See Appendix B for a list of I/O error codes.
NO ROOM	Indicates that the requested operation could not be performed because there was not enough free memory.
WHERE?	Indicates that the * LABEL named in a U: (USE) or J: (JUMP) command does not exist in the program storage area.
U: TOO DEEP	The program has exceeded eight levels of nested USE commands.
DIVIDE BY 0	A COMPUTE command has just attempted to perform a division

2 CORE PILOT



T: Type

The T: (TYPE) command tells the computer to display what you type. You must type T: first, then your message. For instance, T:HELLO will cause the computer to respond *HELLO* as you see in Figure 2-1.



Figure 2-1

The T: command will display anything you can type from the keyboard *literally*. That is, the T: command will not add 2 + 2; it will display it as 2 + 2 (see Figure 2-2).





Figures 2-3 and 2-4 are examples of programs using the T: command. Notice that Figure 2-4 uses graphics characters that are created by holding down the CTRL key while typing the letters.

10 T:THIS IS 20 T:A VERY SHORT 30 T:PROGRAM



Figure 2-3





Figure 2-4

The backslash (\setminus) has a special meaning to the T: command. Rather than printing the next output on a separate line, the backslash tells the computer to continue on the same line (see Figures 2-5 and 2-6).

Note: The computer will automatically move to the next line when it runs out of room.

10 T:THIS WILL \ 20 T:ALL PRINT \ 30 T:ON ONE LINE. RUN



Figure 2-5

10 T:DO YOU READ ME? \ 20 A: 30 T:GOOD





When a T: command sees a string (\$) or numeric (#) variable, it automatically replaces those variable names with their contents if they have been given a value (see Figure 2-7).

```
10 T:WHAT'S YOUR NAME? \
20 A:$NAME
30 T:HOW OLD ARE YOU? \
40 A:#A
50 T:$NAME IS #A YEARS OLD.
READY
```





Figure 2-7



Figure 2-8

The A: command also lets you give a value to a string (\$) or numeric (#) variable as shown in Figures 2-9 and 2-10.





Figure 2-9



10 R:AGE OLD PROGRAM 20 T:HOW OLD ARE YOU? 30 A:#Y 40 C:#L=100-#Y 50 T:JUST THINK, IN #L YEARS, 60 T:YOU'LL BE 100.

READY



Figure 2-10

1

Match



The M: command matches the answer entered by a user (during an A: command) with one or more answers expected by the program. Also, M: automatically creates a YES or NO condition — Yes (Y) there was a match, or NO (N) there was no match. Figure 2-11 shows how this works.

10 R:WEATHER TO DO 20 T:HOW'S THE WEATHER OUTSIDE? 30 A: 40 M:NICE,GOOD,HOT,GREAT 50 TY:GOTO THE PARK AND PLAY. 60 TN:STAY HOME AND READ A BOOK. 70 E: READY HOW'S THE MEATHER OUTSIDE? GOOD GOTO THE PARK AND PLAY. READY



Figure 2-11

In Figure 2-11, if the answer matches *nice*, *good*, *hot*, or *great*, the program types "Go to the park and play" (line 50). If the answer does not match, the program types "Stay home and read a book" (line 60).

In the list of match choices, if you put a space followed by a single letter, the computer will match anything starting with that letter. For example, in Figure 2-12 below, the M:(space)Y will match any word that starts with the letter Y; this would include YES, YUP, YEAH, YOU BET, or even YUK!

10 R:WAVES 20 *WATER 30 T: 40 T: 50 T: 50 T: 60 T:MORE WAVES? \ 70 A: 80 M: Y,OK,O.K.,ALRIGHT,SURE 90 JY: *WATER 100 E: READY

MORE WAVES? SURE MORE WAVES? YOU BET MORE WAVES? YUK MORE HAVES? NO MORE READY

Figure 2-12

Note: The JY: command in line 80 of Figure 2-12 is a conditional JUMP command. See J: (JUMP) or Section 6, Conditionals, for an explanation.

The computer will look to see if any of the choices in a match list are contained, exactly, in any part of an answer. The program in Figure 2-13 below will match on SAL or SAM as any part of the answer. This means that all of the following will create a match: SAL-LY, SALT, SALAD, SALUTE, SALAMI, SAMMY, SAMUEL, and SAME.

10 R:SAM'S & SALLY'S PROGRAM 20 T:HI, WHAT'S YOUR NAME? 30 *AGAIN A: \$NAME 40 M:SAM,SAL 50 TN:I ONLY TALK TO PEOPLE NAMED 60 TN:SAM OR SALLY . . . 70 TN:PLEASE TELL ME YOUR NAME AGAIN: 80 JN:*AGAIN 90 TY:NICE TO MEET YOU, \$NAME. 100 E:

READY



Figure 2-13

Jump



The J: (JUMP) command lets you jump from one spot in a program to another. The J: is ALWAYS followed by a * LABEL indicating to which statement you want to jump. The destination of your J: command must also be labeled with the same * LABEL.

Figure 2-14 shows how the J: command can be used to make a simple loop. The program keeps looping (repeating), filling the screen with *ROUND ROBIN*.

10 R:LOOPING PROGRAM 20 *OVER 30 T:ROUND ROBIN \ 40 J: *OVER

READY



Figure 2-14

Note: Figure 2-14 is an example of a never-ending loop. To stop it, press the BREAK key.

* LABELS can stand alone as in line 20 of Figure 2-14, or they can be placed in front of another command, as in lines 70 and 130 in Figure 2-15. This screen also shows you how the J: command is used conditionally following an M: command. That is, JY: (JUMP only if there is a match), or JN: (JUMP if there is no match).

10 R:RIDDLE PROGRAM 20 T:DO YOU LIKE RIDDLES? \ 30 A: 40 M:YES,YUP,YEAH,SURE,OK, 0.K.,ALRIGHT 50 JN:*BYE 60 T:OK, HERE'S A RIDDLE FOR YOU: 70 *AGAIN T:WHAT'S BLACK AND WHITE AND RED ALL OVER? 80 A: 90 M:SUNBURNED PENGUIN 100 TN:NOPE, GUESS AGAIN 110 JN:*AGAIN 120 T:TERRIFIC; YOU GOT IT! 130 *BYE T:SEE YOU AROUND. 140 E: READY



Figure 2-15



Any time you want to do arithmetic in PILOT, you must use the C: (COMPUTE) command with numeric variables. As an example, the program in Figure 2-16 lets you input two numbers, and then it computes their average (#A).

```
10 R:AVERAGE PROGRAM

20 *DOAGAIN

30 T:THIS PROGRAM COMPUTES THE

AVERAGE

40 T:OF THO NUMBERS

50 T:

60 T:FIRST NUMBER? \

70 A:#F

80 T:SECOND NUMBER? \

90 A:#S

100 C:#A=#F+#S/2

110 T:

120 T:THE AVERAGE OF #F AND #5 IS

#A.

130 T:

140 J:*DOAGAIN

READY
```



Figure 2-16

Note: PILOT will evaluate arithmetic expressions from left to right unless you have used parentheses to show a different grouping.

The C: command is often used to count things in a program. For example, you might want to give a person three chances at answering a riddle. A numeric variable such as #G is used to keep track of the number of guesses made so far. A numeric condition is used to find out whether or not #G has reached the limit (three in this case). Figure 2-17 below shows you how this looks in a program.

10 R:THREE GUESSES
20 C:#G=1
30 T:HERE'S A RIDDLE.
40 T:YOU GET 3 GUESSES:
50 *AGAIN T: WHAT KIND OF PERSON
LOVES COCOA?
60 A:
70 M: COCONUT , COCOANUT , COCOA
NUT .
NUT
90 JY:*BYE
100 J(#G=3): *NOMORE
110 T:NOPE, GUESS AGAIN
120 C:#G=#G+1
130 J:*AGAIN
140 *NOMORE T: SORRY, THAT'S 3
GUESSES.
150 T: THE ANSWER IS
160 PA:90
170 T: ''A COCOA NUT. ''
180 *BYE T: BYE BYE
190 E:
READY

HERE'S A RIDDLE. YOU GET 3 GUESSES: WHAT KIND OF PERSON LOVES COCOA? A COCOA LOVER NOPE, GUESS AGAIN . . . WHAT KIND OF PERSON LOVES COCOA? A COCOA LOCO NOPE, GUESS AGAIN . . . WHAT KIND OF PERSON LOVES COCOA? A COCOA MONSTER SORRY. THAT'S 3 GUESSES. THE ANSWER IS . . . A COCOA NUT.'' BYE BYE. READY

Figure 2-17

Note: The numeric conditional in the J: command in line 100 is explained in Section 6.

You may also use the C: (COMPUTE) command to give a value to a string (\$) variable within a program. For example, the program in Figure 2-18 keeps adding one more star (*) to the value of the string variable \$GROW until the value reaches 21 stars.

```
10 R:GROWING STARS
20 C:$GROW=
30 C:$STAR=*
40 C:#C=0
50 *LOOP
60 C:#C=#C+1
70 C:$GROW=$GROW$STAR
80 T:$GROW
90 J(#C{21}:*LOOP
100 E:
READY
```



Figure 2-18

RANDOM NUMBERS



Besides the examples above, the C: (COMPUTE) command will let the computer select numbers at random. For example, if all the numbers allowed by PILOT were mixed up in a large fish bowl, the computer would reach into the bowl and choose one by chance. The random number is expressed as a ? for the value of a numeric variable in a C: command. For example,

C:#R=?.

The program in Figure 2-19 generates random numbers and types them out.

```
10 R:RANDOM NUMBERS
20 *AGAIN
30 C:#R=?
40 T:#R
50 J:*AGAIN
READY
```



Figure 2-19

You can tell the computer only to select random numbers from 0 through an upper limit. Simply place a backslash ($\$) and the upper limit *after* the question mark (?). For example, C:#R = ? $\$ 10 will choose a random number from 0 through 9. The COIN TOSS program in Figure 2-20 randomly generates only 0's (HEADS) and 1's (TAILS).

10	R:COIN FLIP
	MORE
30	C:#R=?\2
40	T(#R=0):HEADS
50	T(#R=1):TAILS
60	J: *MORE
RE	ADY

		-
HEADS		
HEADS		
TAILS		1000
TAILS		Constanting of
TAILS		
TAILS		
HEADS		
TAILS		
HEADS		
HEADS		
TAILS TAILS		
TAILS		
HEADS		
and the second se		Caller and
		and the second s

A numeric variable can be used as the upper limit for selecting a random number. For example, the program in Figure 2-21 allows you to type in the maximum amount that a drunkard will turn at each step as he staggers for 200 paces.

10 *DRUNKWALKER	
20 GR:CLEAR	
30 T:ENTER MAXIMUM TURN (0-360):\	
40 A:#R	
50 T:> CCLEAR SCREEN]	
60 T: DRUNKEN WALKER MAX. TURN =	
#R D EG.	
70 C:#C=0	
80 MALK	
90 GR : DRAW 5	1000
100 PA:5	
110 GR: TURN ?\#R	1.50
120 C:#C=#C+1	
130 J(#C(200):*WALK	
140 E:	1
READY	
-	





The GUESS MY NUMBER program in Figure 2-22 gives you a more complete example of how you can use the random number feature of PILOT.

10 R:GUESS MY NUMBER 20 T:I'M THINKING OF A NUMBER 30 T:FROM 1-100 40 T: 50 T:TRY TO GUESS WHAT IT IS. 60 T: 70 T:I WILL TELL YOU IF YOUR GUESS 80 T:FORMED OF FORMULAR 80 T: TOO LOH OR TOO HIGH. 90 T: 100 T: ARE YOU READY TO PLAY? 100 HINE FOR ALRIGHT 120 M:Y,SURE,OK,ALRIGHT 130 JN:*BYE 140 *BEGIN 140 #BEGIN 150 T:T [CLEAR THE SCREEN] 160 C:#R=?\100+1 170 C:#C=0 180 T:OK, I HAVE A NUMBER IN MIND. 190 T: 200 #AGAIN 210 T: 220 T:YOUR GUESS? \ 230 A:#G 240 C:#C=#C+1 250 T(#G(#R): TOO LOW; GUESS AGAIN . . . 260 T(#G>#R): TOO HIGH, GUESS AGAIN ... 270 J(#G(>#R):*AGAIN 280 T:YOU GOT IT...IN ONLY #C GUESSES! GUESSES! 290 U:*BEEP 300 T: 310 T:DO YOU WANT TO PLAY AGAIN? \ 320 A: 330 M:Y,SURE,OK,ALRIGHT 340 JY:*BEGIN 350 *BYE T:OK, SEE YOU AROUND. 360 E: 370 *BEEP 380 C:#N=0 390 C:#5=10-#C 400 *BEEPAGAIN 410 50:13 410 50:13 420 PA:8 430 50:0 440 C:#N=#N+1 450 J(#N(#5):*BEEPAGAIN 460 50:13,17,20,25 470 PA:60 480 50:0 490 E: READY

I'M THINKING OF A NUMBER FROM 1-100. TRY TO GUESS MHAT IT IS. I WILL TELL YOU IF YOUR GUESS IS TOO LOO OR TOO LOOG. ARE YOU READY TO PLAY? YES

OK, I HAVE A NUMBER IN MIND. YOUR GUESS? 50 TOD LOT; GUESS AGAIN . . . YOUR GUESS? 85 TOO LOT; GUESS AGAIN . . . YOUR GUESS? 95 TOO LOT; GUESS AGAIN . . . YOUR GUESS? 98 TOO LOT; GUESS AGAIN . . .

YOUR GUESS? 99 You got IT . . . IN ONLY 5 GUESSES!

DO YOU HANT TO PLAY AGAIN?

Figure 2-22



The E: command marks the END of something. In Figure 2-23 below, it marks the END of your program.



Figure 2-23

The end of a program is not necessarily the last line of the program. In Figure 2-24, the E: command is used to mark the END of the program at line 70, and it is also used to mark the END of the ***** TRUMPETS module at line 120.

10	R:FANFARE PROGRAM
20	T:WELCOME TO PILOT
30	U:*TRUMPETS
40	PA:10
50	U:*TRUMPETS
60	T: THE END
70	E:
80	*TRUMPETS
90	50:1,5,9,13
	PA:120
110	50:0,0,0,0
120	

READY -

WELCOME TO PILOT READY

Figure 2-24



The U: command tells the computer to USE a module. A module is a program (subprogram) within a program.

Every module must begin with a * LABEL and must end with an E:. Figure 2-25 shows a module that draws a triangle.

```
100 *TRIANGLE

110 GR: 3(DRAW 30; TURN 120)

120 E:

READY

Figure 2-25
```

If you type U: ***** LABEL in *Immediate* mode, you can check out a module without runing the entire program. For example, Figure 2-26 is the result of typing U: ***** TRIANGLE.



Figure 2-26

Figure 2-27 shows the ***** TRIANGLE module within a larger program. When the computer sees U: ***** TRIANGLE, it jumps to the statement labeled ***** TRIANGLE and uses that module. At the end of the module, the computer continues with the command following U: ***** TRIANGLE.

```
10 R:WHEEL OF TRIANGLES
20 C:#T=0
30 GR:CLEAR
40 *AGAIN C:#T=#T+1
50 U:*TRIANGLE
60 GR:TURN 36
70 J(#T(10):*AGAIN
80 E:
100 *TRIANGLE
110 GR:3(DRAW 30; TURN 120)
120 E:
READY
```

Figure 2-27

The program in Figure 2-27 uses the ***** TRIANGLE module ten times to draw a wheel of triangles. The final result of this program is shown in Figure 2-28 below.



Figure 2-28

Figure 2-29 shows a program that uses several modules (* BOX, * TRIANGLE, * MOON, and * STAR) to make a picture.

10 R:PICTURE 20 GR:CLEAR 30 GR:GOTO -25,-10 40 GR:PEN BLUE 50 U:*BOX 60 GR:TURNTO 30;GO 25 70 GR:PEN RED 80 U:*TRIANGLE 90 GR:GOTO 0,25 100 GR:PEN YELLOW 110 U:*MOON 120 GR:GOTO -40,25 130 U:*STAR 140 GR:GOTO -10,35 150 U:*STAR 160 GR:GOTO 35,20 170 U:*STAR 160 GR:GOTO 35,20 170 U:*STAR 160 GR:SIDRAW 25;TURN 90) 420 GR:SIDRAW 25;TURN 90) 430 GR:FILL 25 440 E: 500 *TRIANGLE 510 GR:TURNTO 150 520 GR:2(DRAW 25;TURN 120);FILL 24 530 E: 600 *MOON 610 GR:TURNTO 70 620 GR:SCTURN -20;FILL 5) 630 GR:TURNTO 50 640 GR:SCTURN -20;FILL 5) 650 E: 700 *STAR 710 GR:SCDRAW 10;TURN 144) 720 E: READY

- 2


Figure 2-29

Note: It is possible to have modules used within modules up to eight layers deep. For example, the ***** TRIANGLE module could itself use a ***** FILL module; the ***** FILL module could use a ***** PENCOLOR module, and so on.

R: Remark

The R: (REMARK) command lets you say something about the program. However, any REMARKS made will be ignored by the computer when you RUN the program. The only time you see them is when you LIST the program onto the television screen. For example, Figure 2-30 is a program made up almost entirely of REMARKS.

10 R:************************************	
20 R:*	*
30 R:*	*
40 R:* THE NOTHING PROGRAM	*
50 R:*	*
60 R:*	*
70 R:**********************	-
80 T: [THIS IS ALSO A REMARK]	
90 T: THIS PROGRAM DOES NOTHIN	16
100 R: THAT'S FOR SURE!	
110 R: THIS IS THE END OF THE	
PROGRAM.	
120 E:	
READY	

Figure 2-30

Note: Square brackets [] are used to indicate a remark on the same line as a command as shown in line 80 above.

When you type **RUN** and press **RETURN**, Figure 2-31 is all you will see on the screen.



Figure 2-31

REMARKS are particularly helpful when you write longer programs because they will remind you how the program works long after you have written it.





AUTO

Automatic Line Numbering

Use the AUTO command when you want to type a program into the computer memory. AUTO *automatically* numbers your program lines for you.

While you are in the AUTO mode, the computer will make everything you type part of your program. No Immediate mode commands can be entered until you exit from the AUTO mode by pressing the **RETURN** key.

When you type **AUTO** your screen turns yellow as in Figure 3-1. When you leave the AUTO mode, your screen turns blue.



Figure 3-1

Remember that the computer enters the line numbers, which you cannot see until you exit from the AUTO mode and LIST the program.

Figure 3-2 shows a program entered in the AUTO mode.



Figure 3-2



Figure 3-3

You can tell the AUTO command where to start numbering and by how much to increase each new line number. For example, AUTO 100,20 tells the computer to begin numbering at 100 and increase each line by 20 (if you leave off the second number, it will automatically increase by 10's).

Run a Program





The RUN command tells the computer to execute the program currently in memory. Figure 3-4 shows a listed program and Screen 3-5 shows the program after RUN is typed.



Figure 3-4



Figure 3-5

LIST List a Program





LIST tells the computer to display the program currently stored in memory. Use this command anytime you need to see the entire program, a few lines of the program, or just one line of the program. For example, Figure 3-6 shows the listing of an entire program.



Figure 3-6

The command LIST 40,80 tells the computer to start listing at line 40 and end at line 80, as you see in Figure 3-7.

	LIST 40,80 40 C:#S=1 50 *AGAIN 60 GR:5(DRAW #5;TURN -72) 70 GR:DRAW 9;TURN -#5/3 80 C:#S=#S+1	
	READY	
L		J



The command LIST 50 tells the computer to LIST only line 50, as you see in Figure 3-8.



Figure 3-8

Note: To get a printed listing of your program on paper, you must SAVE your program to the printer (see the SAVE command).

REN Renumber a Program

The REN command renumbers the program statements, beginning with the first line of the program. It renumbers the lines by 10's, starting at 10, so you can add more lines of program if necessary. Figure 3-9 shows a program before renumbering.



Figure 3-9

Figure 3-10 shows the same program renumbered by 10's starting with 10.



Figure 3-10

REN will also let you begin renumbering at any number and increase each statement by any amount you want. For example, **REN 100,5** will renumber your program statements starting at 100 and increase each line by 5's.

Figure 3-11 shows the program in Figure 3-10 renumbered, starting at 100, increasing by 5's.

READY LIST 100 R:SILLY RIDDLE PROGRAM 105 T: 110 T:WHY ARE ALL BIRDS IN DEBT? 115 T:	
100 R:SILLY RIDDLE PROGRAM 105 T: 110 T:WHY ARE ALL BIRDS IN DEBT?	
105 T: 110 T:WHY ARE ALL BIRDS IN DEBT?	
105 T: 110 T:WHY ARE ALL BIRDS IN DEBT?	
115 T:	
120 A:	
125 T:	
130 M: BILLS	
135 TN:NOPE.	
140 TN:BIRDS ARE IN DEBT	
145 TN: BECAUSE THEY ALL HAVE BILLS.	
150 TY: THAT'S RIGHT!	
155 E:	
READY	
	11

Figure 3-11



The NEW command lets you erase the program in the computer memory. You must be careful when you use this command. Make sure you do not want the program any more before typing **NEW**.

110 E: READY

Figure 3-12 shows the listing of a program before **NEW** is typed.

Figure 3-12

Figure 3-13 shows the attempted listing of a program after NEW is typed.



Figure 3-13

VNEW New Variables

The VNEW: command clears the numeric and/or string variables by using the command as follows:

VNEW:\$	(clears the string variables)		
VNEW:#	(clears the numeric variables)		
VNEW:	(clears both string and numeric variables)		

The VNEW: command does not erase the program from memory.

Figure 3-14 shows a program with string and numeric variables.



Figure 3-14

Figure 3-15 shows the variables with values assigned.



Figure 3-15



Figure 3-16 shows the variables after **VNEW** has been typed.



Figure 3-16

DUMP Dump String Variables

If you want to see the contents of all the string variables in the computer's memory, type **DUMP** and press the **RETURN** key. The DUMP command does not clear the memory, and therefore is helpful when you want to find errors in your program.

The program in Figure 3-17 is a listing of a program.

10 R:A MAD LIB 20 T:PLEASE ANSWER THESE QUESTIONS: 30 T:NAME AN UGLY COLOR: \ 40 A:SCOLOR 50 T:NAME A CITY: \ 60 A:SCITY 70 T:NAME A FAMOUS MOVIE STARLET? \ 80 A:STARLET 90 T:WHAT'S YOUR GREATEST FEAR? 100 A:SFEAR 110 T: J [CLEAR SCREEN] 120 T: NEWS FLASH 130 T: 140 T:LAST WEEK, THE FAMOUS ACTRESS, 150 T:SSTARLET, TRAVELED TO SCITY 160 T:WEARING DARK SUNGLASSES AND A 170 T:SCOLOR HAT SO THAT NO ONE WOULD 180 T:KNOW THAT SHE WAS AFRAID OF 190 T:SFEAR. 200 T: THE END 210 E: READY

Figure 3-17

Figure 3-18 is a RUN of that program.





Figure 3-18

Figure 3-19 is a DUMP of the variables in that program.



Figure 3-19

LOAD Load a Program



The LOAD command tells the computer to LOAD a program you have saved on cassette or diskette into the computer memory.

LOAD C: Loading From Cassette

In order to LOAD a program from cassette (indicated by C:), type LOAD C: and press the RETURN key.

The computer will beep, signaling you to position the cassette tape and press the PLAY button on the cassette recorder. When you are ready, press **RETURN** on the computer console to start the tape loading. If you turn up the volume control on your television set, you will soon hear a series of beeps. This tells you that the cassette is loading properly.

LOAD D: FILENAME Loading From Diskette

If you are loading a program saved on a diskette, you must know the name of the program. For example, if the name of the program you want to LOAD is COLORS.PLT, you would type **LOAD D:COLORS.PLT** and press the **RETURN** key. The *D*: tells the computer you are loading from the disk drive. Again, if the volume control is turned up on the television set, you will begin hearing a series of fast beeps telling you that a program is being loaded.

MERGING PROGRAMS

The LOAD command does NOT clear out memory before loading a program. This allows you to merge two programs — that is, load one program into memory on top of another one. When you merge two programs, the program loaded last will write over and replace any statements having *the same* line numbers as the first program.

Note: Unless you want to merge two programs, you should always type **NEW** to clear memory before loading a program.

Figures 3-20 and 3-21 show two different programs, Program One and Program Two.

```
5 R: PROGRAM ONE
5 R:PROGRAM ONE
10 R:CITYSCAPE
20 GR:CLEAR
30 U:*BUILDINGS
40 U:*SKY
50 T: THECI
80 E:
                      THE CITY AT NIGHT
80 E:

100 *BUILDINGS

110 GR:GOT075,-31;CLEAR

120 C:#D=0

130 C:#L=1

140 *NEXTBUILD

150 C:#C=?\3+1 [RANDOM COLOR]

160 J(#C=#L):*NEXT BUILD

170 GR(#C=1):PEN RED

180 GR(#C=2):PEN YELLOW

190 GR(#C=3):PEN BLUE

200 C:#X=?\15+5 [RANDOM BLDG
200 C:#X=?\15+5 ERANDOM BLDG
WIDTH]
210 C:#Y=?\30+5 [RANDOM BLDG
HEIGHT]
220 GR: TURNTO 0; DRAW #Y; TURNTO
180;G0 #Y
230 GR: TURNTO -90;GO #X;TURNTO 0;
240 C:#D=#D+#X
250 C:#L=#C
260 GR:TURNTO 180;60 #Y
270 J(#D(150):*NEXTBUILD
300 *5KY
310 GR:PEN YELLOW
320 C:#N=0
330 *MORE
340 C:#X=?\158-79
```

```
350 C:#Y=?\50+5

360 GR:GOTO #X,#Y

370 GR:S(DRAH 4;TURN 144)

380 C:#N=#N+1

390 J(#N(20):*MORE

400 E:

READY
```



Figure 3-20





Figure 3-21

Figure 3-22 shows what happens if you LOAD Program Two on top of Program One.



400 GR(#C=3):PEN YELLOW 410 GR:TOTO #X,#Y 420 C:#S=#S+1 430 J(#S(70):*MORESTARS 440 E: 450 *MOON 460 GR:PEN YELLOW 470 GR:TURNTO 70 480 GR:38(DRAW 1;TURN 5) 490 GR:TURNTO 50 500 GR:5(TURN -20;FILL 5) 510 E:







Save a Program



The SAVE command lets you save all or any part of a program you have written. In order to SAVE a program, you must have either a cassette or disk drive attached to your computer. You can get a printout by saving your program to the printer.

SAVE C: Save to Cassette

To SAVE a program to cassette, type **SAVE C:**. The computer will beep twice, which tells you to position the cassette type, and press the PLAY and RECORD buttons (at the same time). Then press the **RETURN** key on the computer console to begin saving your program. As this occurs, you will hear a high-pitched hum and a series of low beeps. When you SAVE to cassette in PILOT, you cannot give the program a name. You must make a note as to the location of the program on the tape by the numbers shown in the counter window on the recorder. Then when you want to LOAD the program back into memory, you must first move the tape until that number shows in the counter window.

If you want to SAVE only part of your program, you need to type the line numbers you want saved. For example, typing **SAVE C:10,50** will SAVE lines 10 through 50 to the cassette.

Save to Diskette

If you are saving to a diskette, you must give the program a name of up to seven characters. You can extend the program name by adding a period and three more characters. This is helpful if you have more than one version of a program. For example, if Version 3 of your COLOR program was in memory and you wanted to SAVE it on a diskette, you might type:

SAVE D:COLORS.V03

The disk drive will start humming, and if your television volume control is turned up slightly, you will hear the beeps telling you that the program is being saved.

If you are saving only part of the program to diskette, you need to type in the lines you want saved after the program name. For example, typing **SAVE D:MODULE1 10,50** will SAVE only lines 10 through 50 on the diskette under the program name, "MODULE1."

SAVE P: Save to Printer

To get a listing of part or all of your program printed on paper instead of the television screen, you must SAVE your program to the printer. To get a listing of your whole program, turn on the printer, and type **SAVE P:**. If you only want a listing of lines 20 through 50, type **SAVE P:20,50**.

DOS Disk Operating System

When you want to work with your disk files for any reason, type **DOS** and press **RETURN**. This will bring up the DOS Menu (Figure 3-23) to your television screen.



Figure 3-23

Select the function you want to perform from the DOS Menu, type the letter for that function, and press **RETURN**. For example, if you want to see what files are in the Disk Directory, you would type the letter **A** (see DOS Menu) and press **RETURN** twice. You will then see a listing of all the files in the directory (Figure 3-24). Our sample Disk Directory is listed on the following page; yours will have different filenames.



Figure 3-24







The GR: (GRAPHICS) command tells the computer you are going into the Graphics mode to draw a picture. Figure 4-1 shows you what the basic Graphics screen looks like.



Figure 4-1

The black background is for drawing, and the blue strip at the bottom of the screen (the *text window*) is for displaying messages or writing commands.

TURTLE GRAPHICS

The method by which you draw is called *turtle graphics*. Imagine that the screen is the playground of an invisible turtle who draws on the screen with a tiny pen. The GRAPHICS commands tell the turtle where to go and what to do with the pen.

The GR: command does not draw anything by itself; it must be used with Graphics Subcommands. For example, the PEN Subcommand tells the turtle either to lift the PEN or to draw in one of four colors. The Graphics Subcommands are explained in more detail on the pages to follow.

Commanding the turtle to move is like giving someone directions to the nearest gas station: either you give directions where (go to Fourth and Main St.), or you give specific directions which way and how far (go 3 blocks to Fourth, take a right and go 4 blocks to Main St.).

WHERE TO GO - X AND Y COORDINATES

The Graphics screen is really an invisible grid of numbered lines which looks like a piece of graph paper. The center of the screen is a point (called the *origin*) where the X and Y axes cross.

The X axis goes horizontally from the left (-79) to right (+79). The Y axis goes vertically from the bottom of the screen (-47) to the top of the screen (+47). The bottom of the screen includes the text window.

Every point on the screen is named by two numbers (X,Y). These two numbers are called the **X** and **Y** coordinates of the point. They tell the distance horizontally and vertically from the point to the origin. Figure 4-2 shows the screen layout with some labeled points.



Figure 4-2

The Graphics Subcommands GOTO, DRAWTO, and FILLTO use coordinates to tell the turtle where to go.

WHAT DIRECTION AND HOW FAR TO GO

The turtle is always at the center of an invisible circle which moves with him wherever he goes. This circle is divided into 360 one-degree angles, with the 0-degree angle pointing up.

The turtle is always pointing in some direction within this circle, and can turn to the right (+) or left (-) in 360 different angles. Figure 4-3 shows some different headings. The Graphics Subcommands TURNTO and TURN, change the turtle's direction.



Figure 4-3

Each step the turtle takes, either forward or backward, is called a **turtle unit**. The units are the same size as the individual units making up the invisible grid; therefore, if the turtle moved from the origin to the right edge of the screen, he would move 80 turtle units. The Graphics Subcommands GO, DRAW, and FILL tell the turtle to move forward or backwards in whatever direction he is facing.

INITIAL LOCATION, HEADING, AND PEN COLOR

When you first enter the Graphics mode, the turtle is located at 0,0 (the origin). He is facing 0 degree (straight up) and the PEN color is yellow.

SHORTCUTS FOR GRAPHICS PROGRAMMING

You can program more than one GRAPHICS subcommand in the same program statement. **Each subcommand MUST be separated by a semicolon (;)**. For example:

GR:GOTO 0,0; DRAW 10; TURN 45; PEN RED; DRAW 5

If you want a series of subcommands repeated a specific number of times, enclose the series of subcommands in parentheses and precede the left parenthesis by the number of times you want that series repeated. For example, the program in Figure 4-4 shows the long way to draw a box. The program in Figure 4-5 shows a short way to to draw the same box.

	-	
R:LONG WAY BOX GR:CLEAR GR:CDTO -15,-5 GR:DRAW 30 GR:TURN 90 GR:DRAW 30 GR:TURN 90 GR:TURN 90 GR:TURN 90 GR:TURN 90 GR:TURN 90 GR:TURN 90 GR:TURN 90 GR:TURN 90 GR:TURN 90 GR:TURN 90		
	READY	

Figure 4-4

10 R:SHORT WAY BOX 20 GR:CLEAR 30 GR:GOTO -15,-5 40 GR:4(DRAW 30;TURN 90) 50 E: READY

-

10 R



Figure 4-5

GR:CLEAR Clear the Graphics Screen



GR:CLEAR erases what is on the screen. When you enter a new GR: command the picture begins at the point you left off with the last drawing.

Figures 4-6 through 4-8 show you how GR:CLEAR can be used in a program. The program draws a pentagon, pauses for you to look at it, then clears the screen and draws a star. The program continues to go back and forth between the pentagon and the star, giving you a flashing effect.

> 10 R: THE PENTAGON AND THE STAR GR:CLEAR 20 30 *LOOP U: *PENTAGON 40 50 PA:5 GR : CLEAR 68 78 U:*STAR PA:5 GR:CLEAR 80 98 100 J:*LOOP 110 *PENTAGON 120 GR:GOTO -15,0 130 GR:TURNTO -18 140 GR: 5(DRAH 20; TURN 72) 150 E: 160 *STAR 100 #5148 170 GR:GOTO -15,0 180 GR:TURNTO 19 190 GR:5(DRAM 31;TURN 144) E:

READY







Figure 4-7



Figure 4-8

GR:GOTO Go to the Point X,Y







The command GR:GOTO X,Y tells the turtle to pick up the pen, move to the point with coordinates X and Y, and put the pen down there. The pen leaves a dot on the screen at the point (X,Y). Figure 4-9 is a short program that makes "The Big Dipper" using GOTO commands.

READY



Figure 4-9

The X and Y coordinates in the GOTO command may either be numbers, numeric variables, or numeric expressions. The program in Figure 4-10 uses numeric variables #X and #Y as coordinates. These variables are given random values so the dots appear at random on the screen. (The color of the dots is also chosen at random.)

10 R:NIGHT SKY 20 GR:CLEAR 30 T: NIGHT SKY 40 C:#5=0 50 #MORE 60 C:#X=?\158-79 70 C:#Y=?\47 80 C:#C=?\3+1 90 GR(#C=1):PEN RED 100 GR(#C=2):PEN BLUE 110 GR(#C=2):PEN YELLOW 120 GR:GOTO #X,#Y 130 C:#5=#5+1 140 J(#5{100}):*MORE 150 E:

READY



Figure 4-10

GR:DRAWTO Draw to the Point X,Y







The command GR:DRAWTO X,Y tells the turtle to put the pen down and draw a straight line to the point with coordinates X and Y. The line is drawn in the pen's current color,
and the turtle ends up at point X, Y. For example, the program in Figure 4-11 uses DRAWTO to make the outline of a barn.

10	R:BARN
20	GR:CLEAR
30	GR:PEN RED
40	GR:GOTO -30,40
50	GR:DRAWTO 45,40
60	GR : DRAWTO 60,25
70	GR:DRAWTO 65.5
80	GR:DRAWTO 65.5
90	GR: DRAWTO 65, -30 GR: DRAWTO -10, -30
100	GR: DRAWTO -10,-30
110	GR:DRAWTO -10.5
120	GR:DRAWT0 -15,25 GR:DRAWT0 -30,40
130	GR : DRAHTO -30,40
140	GR: DRAW TO -45,25
150	GR:DRAWTO -50.5
160	GR: DRAWTO -50, -30
170	GR:DRAWTO -10,-30
180	GR:GOTO 65,5
190	GR:DRAWTO -50,5
200	GR:GOTO -35,30
210	GR:DRAWT0 -25.30
220	GR: DRAWTO -25,15
230	GR:DRAWT0 -25,15 GR:DRAWT0 -35,15
240	GR: DRAWTO -35.30
250	GR:GOTO -40,-30
260	GR:DRAWTO -40,-10
270	GR : DRAWTO -20,-10
280	GR : DRAWTO -20,-30
290	E:
REAL	DY



Figure 4-11

The X and Y coordinates in the GOTO command may either be numbers, numeric variables, or numeric expressions. The "Modern Art 1" program in Figure 4-12 uses numeric variables #X and #Y as coordinates. These variables are given random values so the lines are drawn at random. The colors of the lines are also chosen at random.

```
10 R:MODERN ART I
20 *BEGIN
30 GR:CLEAR
40 T:
50 T: MO
60 C:#L=?\200+7
70 C:#5=0
80 *MORE
                     MODERN ART
90 C:#X=?\158-79
100 C:#Y=?\94-47
110 C:#C=?\4
120 GR(#C=0) :PEN UP
130 GR(#C=1) :PEN RED
140 GR(#C=2) :PEN BLUE
150 GR(#C=3) :PEN YELLOW
160 GR : DRAWTO #X, #Y
170 C:#5=#5+1
180
     J(#5(#L) :*MORE
190 PA:1000
200 J:*BEGIN
READY
```





Figure 4-12

GR:FILLTO Fill to the Point X,Y

The command GR:FILLTO X,Y tells the turtle to draw a line to the point with coordinates X and Y. As he moves, the black background between the turtle and any figure or line directly to his right is filled with the current pen color. Figure 4-13 shows how FILLTO is used to fill parts of a barn in red.

10 R:RED BARN
20 GR:CLEAR
30 GR:PEN RED
40 GR:GOTO -30,40
50 GR: DRAWTO 45.40
50 GR: DRAWTO 45,40 60 GR: DRAWTO 60,25
70 GR: DRAWTO 65,5
80 GR : DRAWTO 65,5
90 GR : DRAWTO 65,-30
100 GR: DRAWTO -10,-30
110 GR:FILLT0 -10,5
120 GR:FILLT0 -15,25
130 CD FTI I TO - 30 40
140 GR : DRAWTO -45,25
150 GR: DRAWTO -50,5
160 GR: DRAWTO -50,-30
140 GR:DRAWTO -45,25 150 GR:DRAWTO -50,5 160 GR:DRAWTO -50,-30 170 GR:DRAWTO -10,-30
180 GR: GOTO 65,5
190 GR:PENERASE
200 GR: DRAWTO -10,5
210 GR : PEN RED
220 GR: DRAWTO -50,5
230 GR:GOTO -35,30
240 GR:DRAWT0 -25.30
250 GR:DRAWTO -25,15 260 GR:DRAWTO -35,15 270 GR:FILLTO -35,30
260 GR: DRAWTO -35,15
270 GR:FILLT0 -35,30
280 GR:GOTO -20,-30
290 GR: DRAWTO -20,-10
300 GR: DRAWTO -4010
310 GR:FILLTO -40,-30
320 E:
READY





If there is nothing to block the color filling in before it reaches the right edge of the screen, the filling "wraps around," and color continues to fill in from the left edge until a barrier is reached. When there is nothing blocking the fill anywhere in its path, the line being filled from becomes its own barrier. This is shown in Figure 4-14.

```
10 R:FILLING UP SPACE

20 GR:GOTO 30,45;TURNTO 180;PEN

YELLOW

30 U:*PARTBOX

40 GR:GOTO -40,15;TURNTO 90;PEN

YELLOW

50 U:*PARTBOX

60 GR:GOTO -50,-20;TURNTO 30;PEN

YELLOW

70 U:*TRIANGLE

80 GR:GOTO 15,0;TURNTO 90;PEN

YELLOW

90 U:*BOX

100 GR:GOTO 50,5;TURNTO -30;PEN

YELLOW

120 U:*TRIANGLE

200 GR:GOTO 50,-30

210 GR:PEN RED

220 GR:FILLTO 50,30

230 GR:PEN YELLOW;GOTO 51,31

299 E:

400 *BOX

410 GR:4(DRAW 10;TURN 90)

420 E:

500 *PARTBOX

510 GR:3(DRAW 20;TURN 90)

520 E:

600 *TRIANGLE

610 GR:3(DRAW 15;TURN 120)

620 E:
```

READY



Figure 4-14

FILLTO, like GOTO and DRAWTO, may use either numbers, numeric variables, or numeric expressions as coordinates.

GR:TURNTO Turn to N Degrees



The command GR:TURNTO N tells the turtle to turn in place until he is heading toward the angle N degrees. The top of the screen is 0 degree. Positive angles (+) are measured clockwise from 0 degree; negative angles (-) are measured counterclockwise.

Since the turtle is invisible on the screen, you cannot see him turn, but you can see the direction of his new heading by executing a GO, DRAW, or FILL command after the TURNTO. Figure 4-15 shows a program that uses TURNTO to let you make a design on the screen with right angles and 10-unit lines.

10 R:SKETCHING PROGRAM 28 T: THIS PROGRAM LETS YOU DRAW A **30 T:DESIGN ON THE GRAPHICS** SCREEN 40 T:USING THE COMMANDS: 50 T: 60 T:UP 70 T:DOWN 80 T:RIGHT 90 T:UEFT 100 T: LEAR 110 T: 120 T:PRESS RETURN TO BEGIN . . . 130 A: 140 *BEGIN 150 GR:CLEAR 160 T:STARTING X LOCATION? \ 170 A:#X 180 TISTARTING Y LOCATION? 190 A:#Y 200 GR:GOTO #X,#Y 210 *COMMAND 220 T: WHICH WAY (O D OF BLEAR)? \ 238 A: 240 M: U, D, R, L, C 250 JM:*UP,*DOWN,*RIGHT,*LEFT, *BEGIN 260 HUP GR : TURNTO 0 270 J:*LINE 280 *DOWN GR:TURNTO 180 290 J:*LINE *RIGHT GR : TURNTO 90 388

310 J:*LINE 320 *LEFT GR:TURNTO -90 330 *LINE GR:DRAW 10 340 J:*COMMAND

READY



Figure 4-15

The directional angle, N, in the GR:TURNTO N command may be either a number, a numeric variable, or a numeric expression. The program in Figure 4-16 uses TURNTO with the numeric variable, #T, to create a starburst pattern with lines coming out from the origin every 5 degrees.

```
10 R:STARBURST
20 C:#T=0
25 GR:CLEAR
30 *LOOP
40 GR:GOTO 0,0
50 GR:TURNTO #T
60 GR:GO 3;DRAW 25
70 C:#T=#T+5
80 JC#T(360):*LOOP
90 E:
READY
```



Figure 4-16

GR:TURN Turn N Degrees



The command GR: TURN N tells the turtle to turn N degrees clockwise (+N) or counterclockwise (-N) from the direction he is currently facing. Since the turtle is invisible on the screen, you cannot see him turn, but you can see the direction of his new heading by executing a GO, DRAW, or FILL command after the TURN. Figure 4-17 shows a program that makes a 13-pointed star with a 166-degree turn at each point.

10 R:13-POINTED STAR 20 C:#C=0 30 GR:CLEAR 40 GR:GOTO -10,-5 50 GR:TURNTO 14 60 *LOOP 70 GR:DRAW 50 80 GR:TURN 166 90 C:#C=#C+1 100 JC#C(14):*LOOP 110 E: READY



Figure 4-17

The directional angle N, in the TURN (N degrees) command can be either a number, a numeric variable, or a numeric expression. The program in Figure 4-18 draws first a triangle, then a square, then a pentagon, and so on, all on top of each other. The amount the turtle turns in line 90 is 360 degrees divided by the number of sides in the polygon he is currently drawing.

10 R:EUCLID 20 C:#S=3 30 GR:CLEAR 40 *BEGIN 50 C:#C=0 60 GR:GOTO 10,-30 70 GR:TURNTO -90 80 *LOOP 90 GR:DRAW 20;TURN 360/#S 100 C:#C=#C+1 110 JC#C(#S):*LOOP 120 C:#S=#S+1 130 JC#S(21):*BEGIN 140 E:	
30 GR:CLEAR 40 *BEGIN 50 C:#C=0 60 GR:GOTO 10,-30 70 GR:TURNTO -90 80 *LOOP 90 GR:DRAW 20;TURN 360/#5 100 C:#C=#C+1 110 JC#C(#5):*LOOP 120 C:#S=#5+1 130 JC#5(21):*BEGIN 140 E:	10 R:EUCLID
40 *BEGIN 50 C:#C=0 60 GR:GOTO 10,-30 70 GR:TURNTO -90 80 *LOOP 90 GR:DRAW 20;TURN 360/#5 100 C:#C=#C+1 110 JC#C(#5):*LOOP 120 C:#S=#5+1 130 JC#S(21):*BEGIN 140 E:	20 C:#5=3
50 C:#C=0 60 GR:GOTO 10,-30 70 GR:TURNTO -90 80 *LOOP 90 GR:DRAW 20;TURN 360/#5 100 C:#C=#C+1 110 JC#C(#5):*LOOP 120 C:#5=#5+1 130 JC#5(21):*BEGIN 140 E:	30 GR:CLEAR
50 C:#C=0 60 GR:GOTO 10,-30 70 GR:TURNTO -90 80 *LOOP 90 GR:DRAW 20;TURN 360/#5 100 C:#C=#C+1 110 JC#C(#5):*LOOP 120 C:#5=#5+1 130 JC#5(21):*BEGIN 140 E:	40 *BEGIN
60 GR:GOTO 10,-30 70 GR:TURNTO -90 80 *LOOP 90 GR:DRAW 20;TURN 360/#5 100 C:#C=#C+1 110 J(#C(#5):*LOOP 120 C:#5=#5+1 130 J(#5(21):*BEGIN 140 E:	
70 GR:TURNTO -90 80 *LOOP 90 GR:DRAW 20;TURN 360/#5 100 C:#C=#C+1 110 J(#C(#5):*LOOP 120 C:#5=#5+1 130 J(#5(21):*BEGIN 140 E:	
80 *LOOP 90 GR:DRAW 20;TURN 360/#5 100 C:#C=#C+1 110 JC#C(#5):*LOOP 120 C:#5=#5+1 130 JC#5(21):*BEGIN 140 E:	78 GR : TURNTO -98
90 GR:DRAW 20;TURN 360/#5 100 C:#C=#C+1 110 JC#C(#5):*LOOP 120 C:#5=#5+1 130 JC#5(21):*BEGIN 140 E:	
100 C:#C=#C+1 110 JC#C(#5):*LOOP 120 C:#5=#5+1 130 JC#5(21):*BEGIN 140 E:	
110 J(#C(#5):*LOOP 120 C:#5=#5+1 130 J(#5(21):*BEGIN 140 E:	100 C:#C=#C+1
120 C:#5=#5+1 130 J(#5(21):*BEGIN 140 E:	
130 J(#5(21):*BEGIN 140 E:	
140 E:	
	130 J(#5(21):*BEGIN
	140 E:
READY	READY

READY

Figure 4-18











The GR:GO N command tells the turtle to pick up the pen, move N units in the direction he is facing, and put the pen down there. The turtle leaves a dot on the screen at the location where he ends up. The program in Figure 4-19 uses the GO command to draw a box with dotted lines.

10 R:DOTTED BOX 20 GR:CLEAR 30 GR:4(10(GO 3) ;TURN 90) 40 E: READY



Figure 4-19

The number of units, N, in the GR:GO N command can be either a number, numeric variable, or a numeric expression. The program in Figure 4-20 tells the turtle to take a "random walk." That is, he starts at the origin, turns a random number of degrees, goes a random number of units, turns at random again, moves at random again, and so on. At the end of this walk, all the places he stopped and turned are marked by dots on the screen.

10	R : RANDOM WALK	
	*BEGIN	
30	C:#C=0	
40	GR:CLEAR	
50	T: RANDOM WALK	
	GR : PEN YELLOW; GOTO 0, 0; PEN	RED
70	*LOOP	
80	GR: GO ?\5	
90	GR:TURN ?\360	
	C:#C=#C+1	
110	J(#C(500) :*LOOP	
120	T:	
130	T:END OF WALK	
140	PA:900	
150	J:*BEGIN	
REA	DY	
_		



Figure 4-20









The command GR:DRAW N tells the turtle to draw a line, N units long, moving in the direction he is currently facing. The line is drawn in the current pen color. The program in Figure 4-21 uses the DRAW and TURN commands to make a simple house.

10 R:SIMPLE HOUSE 20 GR:CLEAR 30 T: HOUSE 40 GR:GOTO -15,10 50 GR:TURNTO 90 60 GR:DRAM 30;TURN 90 70 GR:DRAM 30;TURN 90 80 GR:DRAM 30;TURN 90 90 GR:DRAM 30;TURN 120 110 GR:DRAM 30;TURN 120 110 GR:DRAM 30;TURN 120 120 E: READY



Figure 4-21

The number of units, N, in the GR:DRAW N command can be either a number, a numeric variable, or a numeric expression. Figure 4-22 shows a program that draws spirals at any angle you choose. Each time the turtle turns, the side of the spiral grows longer by the amount you type into the computer.

```
10 R:SQUIRAL
20 GR:CLEAR
30 #BEGIN
40 T: SQUIRAL
50 T: 50 T:
60 T:TURNING ANGLE (1-179)?\
70 A:#A
80 T:SPEED OF GROWTH (1-10)? \
90 A:#I
100 GR:CLEAR;GOTO 0,0;TURNTO 0
110 T: SQUIR
                                             SQUIRAL
120
      T:
125 T:ANGLE = #A
                                        GROWTH =#I
130 C:#5=0
140 *MORE
150 GR:DRAW #5;TURN #A
160 C:#5=#5+#I
170 J(#5(200):*MORE
180 T:AGAIN?\
190 A:
170 A:
200 M: Y,SURE,OK,ALRIGHT
210 JY:*BEGIN
220 GR:QUIT
230 E:
READY
```



Figure 4-22

GR:FILL Fill N Units

The GR:FILL N command tells the turtle to draw a line, N units long, moving in the direction he is currently facing. As he moves, the black background between the turtle and any figure or line directly to his right is filled in with the current pen color. Figure 4-23 shows how FILL can be used to draw a solid triangle, square, or circle.

```
10 R:SOLIDS
20 GR:CLEAR
30 T: TRIANGLE SQUARE CIRCLE
40 GR:GOTO -50,8;TURNTO 150;PEN
RED
50 U:*TRIANGLE
60 GR:GOTO -15,10;TURNTO 90;PEN
BLUE
70 U: *SQUARE
80 GR: GOTO 40,10; TURNTO 90; PEN
YELLOW
90 U: *CIRCLE
100 E:
200 *TRIANGLE
210 GR:2(DRAW 20;TURN 120)
220 GR:FILL 19
230 E:
300 *5QUARE
310 GR:3(DRAH 20;TURN 90)
320 GR:FILL 20
330 E:
400 *CIRCLE
410 GR:18(DRAH 2;TURN 10)
420 GR:18(FILL 2;TURN 10)
READY
```



Figure 4-23

Note: To color in a polygon (such as a triangle, square, or circle) using the FILL command, you must first DRAW the right half of the polygon and then FILL the left half. Sometimes, the filled side must be shorter than the drawn side so that the color will be completely contained within the figure. For example, in Figure 4-23, the two *drawn* sides of the triangle are 20 units long, whereas the *filled* side is only 19 units long.

If there is nothing to block the color filling in before it reaches the right edge of the screen, the filling "wraps around," and color continues to fill in from the left edge until a barrier is reached. When there is nothing blocking the fill anywhere in its path, the line from which the filling takes place becomes its own barrier. The "Sunset" program in Figure 4-24 shows how FILL can be used to fill large areas of the screen with color.

10 R:SUNSET 15 GR:CLEAR 20 U:*SUN 30 U:*REDCLOUDS 40 U:*SKY 45 U:*SUNBATH 50 E: 100 *SUNBATH 110 GR:GOTO 0,-13,TURNTO 180;PEN YELLOW 120 GR:FILL 26 130 E: 200 *SKY 210 GR:GOTO 0,10;TURNTO 0;PEN BLUE 220 GR:FILL 37 230 E: 300 *SUN 310 GR:GOTO 0,10;TURNTO 90 320 GR:36CFILL 1;TURN 53 340 E: 400 *REDCLOUDS 410 GR:GOTO 0,10;TURNTO 90;PEN RED 420 GR:36CFILL 1;TURN 53 430 E: 700 F: 430 E: 700 F: 7



Figure 4-24

The number of units, N, in the GR:FILL N command can be either a number, a numeric variable, or a numeric expression.



GR:PEN Choose a Pen Color













The GR:PEN COLOR command tells the turtle to choose a pen color - yellow, red, or blue. For example, the program shown in Figure 4-25 draws polka dots in yellow, red, and blue in random positions on the screen.

```
10 R:POLKA DOTS

20 *BEGIN

30 C:#N=0

40 GR:CLEAR

50 T: POLKA DOTS

60 *POLKA

70 C:#X=?\150-75

80 C:#Y=?\62-31

90 C:#C=?\3+1

100 GR(#C=1):PEN YELLOW

110 GR(#C=2):PEN RED

120 GR(#C=3):PEN BLUE

130 GR:GOTO #X,#Y

140 U:*DOT

150 C:#N=#N+1

160 J(#N(50):*POLKA

170 PA:120

180 J:*BEGIN

190 E:

200 *DOT

210 GR:TURNTO 90

220 GR:10(CRAW 1;TURN 18)

230 GR:10(FILL 1;TURN 18)

240 E:
```

```
READY
```



Figure 4-25

GR:PEN ERASE Set Pen Color to Erase

You can also tell the turtle to draw in the black background color by using the command PEN ERASE. This command lets you "erase" anything you have already drawn by redrawing it in the black background color. Figure 4-26 shows how the PEN ERASE command is used repeatedly to draw a star, erase it, and redraw it in a different place. This gives the effect that the star is moving.

```
10 R:SHOOTING STAR

20 *BEGIN

30 C:#C=0

40 GR:CLEAR

50 T: SHOOTING STARS

60 GR:GOTO -75,40

70 GR:TURNTO 120

80 *LOOP

90 GR:PEN YELLOH

100 U:*STAR

110 GR:PEN YELLOH

100 U:*STAR

110 GR:PEN ERASE

120 U:*STAR

130 GR:GO 5

140 C:#C=#C+1

150 J(#C{32}:*LOOP

160 PA:120

170 J:*BEGIN

180 *STAR

190 GR:SCDRAW 10;TURN 144)

200 E:
```

READY





Figure 4-26

GR:PEN UP Lift the Pen

The PEN UP command tells the turtle to pick up the pen off the screen. While the pen is up, all movement by the turtle will be invisible. To put the pen back "down," you choose a pen color.

0



GR:QUIT Quit the Graphics Mode



The command GR:QUIT lets you leave the Graphics mode and return to Text mode. Figure 4-27 shows you the screen *before* the GR:QUIT command, and Figure 4-28 shows you the screen *after* the GR:QUIT command.







Figure 4-28



5 SOUND AND PAUSE



Sound

The SO: command lets you create musical tones on your computer. You can program up to four tones to play at the same time. Each separate tone is then called a *voice*. When a group of people get together to sing, they divide into several *voices*: bass, baritone, alto, and soprano. When you program SO: commands, you can program several voices to play together. When different voices play a sound at the same time, it is called a *chord*.

The tones you can play in PILOT range from 0 to 31. If you enter the command **SO:13**, you will hear a single tone equal to middle C on a piano. The command **SO:1** produces a tone equal to the note C, one octave below middle C. The command **SO:31** produces the note F sharp, one octave above middle C. **SO:0** turns a tone OFF.

Figure 5-1 shows a piano keyboard with the key numbers corresponding to the PILOT SOUND commands.



Figure 5-1

Typing the commands in Figure 5-2 one at a time will produce a scale.





A scale is a series of notes played one after another. Think of a ladder on which you take one step at a time to go up or down. A scale is similar, only with musical notes being played in a specific order. This particular scale covers the octave between middle C and C above middle C. An octave is a range of notes from one note to another note of the same name (higher or lower).

The program in Figure 5-3 repeatedly moves up and down the scale shown on page 86. When this program is RUN, the computer moves through the SOUND commands so quickly that all the tones blur together, and this scale sounds like a siren. The PA: commands in this program increase the length of time the tones are sounded. Without them, this scale sounds like rumbling static. The PA: command is explained later in this section.

10 R:SIREN 20 *BEGIN 30 50:13 30 50:13 35 PA:1 40 50:15 45 PA:1 50 50:17 55 PA:1 60 50:18 65 PA:1 70 50:20 75 PA:1 80 50:22 85 PA:1 90 50:24 95 PA:1 100 50:25 105 PA:1 110 50:24 115 PA:1 120 50:22 125 PA:1 130 50:20 135 PA:1 140 50:18 145 PA:1 150 50:17 155 PA:1 160 50:15 165 PA:1 170 50:13 180 50:0 190 J:*BEGIN READY

Figure 5-3

The SO: command lets you create sound effects and tunes in your PILOT programs. Figure 5-4 shows how you might use SOUND to reward correct answers in a simple geography quiz program.



Figure 5-4

You may use either numbers or numeric variables to tell the computer which tones to play in a SO: command. Values greater than 31 are reduced to numbers between 0 and 31.

Figure 5-5 shows how the SO: command can be used with a numeric variable to make sound effects for the shooting star program of Figure 4-26.

```
1 GR:QUIT

10 R:SHOOTING STAR WITH SOUND

EFFECTS

20 *BEGIN

30 C:HC=0

40 GR:CLEAR

50 T: SHOOTING STARS

60 GR:GOTO -75,40

70 GR:TURNTO 120

80 C:HS=?\20+1

90 *LOOP

100 C:HS=31-HC

110 SO:HP

120 GR:PEN YELLOW

130 U:*STAR

140 GR:PEN YELLOW

130 U:*STAR

140 GR:PEN YELLOW

130 U:*STAR

160 GR:GO S

170 C:HC=HC+1

180 JCHC(32):*LOOP

190 PA:240

200 J:*BEGIN

210 *STAR

220 GR:SCDRAM HS; TURN 144)

230 E:

READY
```



Figure 5-5

PA: Pause N Units



Use the PA:N command when you want a program to PAUSE for any reason during the RUN of a program. For example, PA: may be used to freeze what is on the screen for a few moments before clearing the the screen. PA: also allows you to write text on the screen a little at a time or to pause for dramatic effect: "The correct answer is.... (pause)...An Embarrassed Zebra." The program in Figure 5-6 pauses for dramatic effect before announcing a lucky number in the PILOT Lucky Number Drawing.

```
10 R:LUCKY NUMBER

20 T:WELCOME TO THE PILOT

30 T:LUCKY NUMBER SWEEPSTAKES

40 T:

50 PA:90

60 T:NOW GET READY ... \

70 PA:90

80 T:HERE WE GO.

90 T:

100 PA:90

110 T:ROUND AND ROUND THE CPU GOES

...

120 T:WHERE SHE STOPS, NOBODY

KNOWS.

130 T:

140 PA:90

150 C:#R=?\30000

160 T:AND THE PILOT LUCKY NUMBER

IS...

170 T:

180 PA:180

190 T:#R

200 T:

210 PA:180

220 T:CONGRATULATIONS TO THE

COMPUTER

230 T:WHOSE SERIAL NUMBER IS #R.

240 E:
```

WELCOME TO THE PILOT LUCKY NUMBER SWEEPSTAKES NOW GET READY . . . HERE WE GO. ROUND AND ROUND THE CPU GOES . WHERE SHE STOPS, NOBODY KNOWS. AND THE PILOT LUCKY NUMBER IS . 26177 CONGRATULATIONS TO THE COMPUTER WHOSE SERIAL NUMBER IS 26177. READY

Figure 5-6

The units in the PA:N command may either be a number or a numeric variable. Each unit is equal to 1/60th of a second. Thus **PA:60** will pause for 1 second; **PA:30** will pause for 1/2 second; **PA:300** will pause for 5 seconds, and so on.

The PA: command is often used in combination with the SOUND command to tell the computer how long to sound one or more voices. For example, the program in Figure 5-7 uses SO: and PA: to add a random three-chord polka to the Polka Dots program of Figure 4-25.

```
10 R:DOTS POLKA
 20 *BEGIN
 30 C:#N=0
 40 GR:CLEAR
50 T:
60 T:
                                            DOTS POLKA
 70 *POLKA
80 C:#X=?\150-75
90 C:#Y=?\62-31
90 C:#Y=?\62-31

100 C:#C=?\3+1

110 GR(#C=1):PEN YELLOW

120 SO(#C=1):13,17,20

130 GR(#C=2):PEN RED

140 SO(#C=2):13,18,22

150 GR(#C=3):PEN BLUE

160 SO(#C=3):15,20,24

170 GR:GOTO #X,#Y

180 U:*DOT

190 U:*DOT

190 U:*UMPAH

200 C:#N=#N+1

210 J(#N(50):*POLKA

220 U:*FINALE

230 J:*BEGIN

240 E:

300 *DOT

310 GR:TURNTO 90
310 GR:TURNTO 90
320 GR:10(DRAW 1;TURN 18)
330 GR:10(FILL 1;TURN 18)
340 E:
 400 *UMPAH
 410 C:#R=#N\3
420 PA(#R=0):20
430 50:0,0.0
440 PA(#R=0):5
450 E:
500 *FINALE
 510 50:13,17,20
520 PA:60
 530 50:13,18,22
540 PA;60
550 50:15,20,24
560 PA:60
 570 50:13,17,20,25
580 PA:120
 590 50:0,0,0
600 PA:480
 610 E:
READY
```



Figure 5-7

The SO: and PA: commands can be used together to make music. The table in Figure 5-8 shows the PAUSE values for various musical notes.

PAUSE VALUES FOR MUSICAL NOTES

Sixteenth Note
Eighth Note
Quarter Note
Half Note
Whole Note

Figure 5-8

The program shown in Figure 5-9 uses SO: and PA: to play the the song "Mary Had a Little Lamb."

10 R	MARY HAD A LITTLE LAMB
20 R	ARRANGED IN 4 VOICES
30 R	FOR COMPUTER
	:#T=0
50 *	
60 C	:#T=#T+1
70 5	0:17,13,8
80 P	A:24
90 5	0:15,13,8
	PA:8
110	50:13,8
	PA:32
130	50:15,13,8
140	PA:32
150	50:17,13,8 PA:32
160	PA:32
170	50:17,13,8 PA:32
180	PA:32
190	50:17,13,8
200	PA:64
210	50:15,12,8
220	PA:32
240	50:15,12,8
	PA:32
260	50:15,12,8 PA:64
270	50:17,13,8
280	PA:32
290	50:20,17,13,8
300	PA:32
	50:20,17,13,8
320	PA:64
330	5P:17,13,8
340	PA:24
	50:15,13,8
360	PA:8
370	50:13,8
380	PA:32

390	50:15,13,8
400	
410	50:17,13,8
420	
430	50:17,13,8
440	
450	50:17,13,8
460	PA:32
470	50:15,12,8
	PA:32
490	50:15,12,8
	PA:32
510	50:17,13,8
520	PA:32
530	50:15,12,8
540	PA:32
550	50:13,8,5,1
560	
570	50:0
580	J(#T(2):*COD4
590	E:
REAL	Y
-	

Figure 5-9

CONDITIONALS



CONDITIONAL COMMANDS



A condition is something about which a YES or NO decision can be made. For example, the weather could be a condition for deciding what to do today: Is it raining outside? If YES, go to the movies; if NO, go flying.

In PILOT, there are two types of conditions:

- String match conditions
- Numeric conditions

Y OR N String Match Conditions

A MATCH command always sets up a YES or NO condition: YES (Y) there was a match, or NO (N), there was not a match. For example, in the program shown in Figure 6-1, any answer containing the name "GRANT" produces a YES condition; any answer not containing "GRANT" produces a NO condition.

10 R:GRANTS TOMB 20 T:WHO WAS BURIED IN GRANT'S TOMB? TOMB? 30 T: 40 A:\$ANYONE 50 M: GRANT 60 T: 70 TY:YES, THAT IS CORRECT. \$ANYONE WAS BURIED IN GRANT'S TOMB. 80 TN:NO, \$ANYONE WAS NOT BURIED IN GRANT'S TOMB; GRANT WAS. 90 T:SEE YOU AROUND. 100 E: READY



Figure 6-1

You can make any PILOT command (T:, A:, M:, J:, C:, U:, E:, GR:, SO:, and PA:) conditional on a YES-match or NO-match by putting a Y or an N between the command and the colon (:). Here are some examples:

TY:HELLO	If there is a match, type "HELLO"; otherwise, skip this command.
TN:WRONG	If no match, type "wrong"; otherwise, skip this command.
EY:	If there is a match, end the program; otherwise, keep going.
JN: * NEXT	If no match, jump to * NEXT; otherwise, skip this command.
UY: * BOX	If there is a match, use the module * BOX; otherwise skip this command.
SOY:13,17	If there is a match, sound notes 13 and 17; otherwise skip this command.

Figure 6-2 shows a program that uses String Match Conditions.

```
10 R:DRAGON FEED

20 T:CAN YOU NAME SOMETHING THAT

30 T:DRAGONS LIKE TO EAT?

40 A:$FOOD

50 M: YES, YUP, OK, FINE,

50 K: YES, YUP, OK, FINE,

50 T: CAN, THINK I CAN, THINK SO

60 T:

70 TY:PLEASE NAME SOMETHING THEN.

80 AY:$FOOD

90 M: NO, NOT, CAN'T, DON'T,

UNSURE

100 TY:SORRY TO HEAR THAT.

110 JY:*YONDER

120 M:PEOPLE, PRIN, KNI, CAKE,

PRETZ, FLOWER

130 T:

140 TY:YES,DRAGONS SURE DO EAT

$FOOD.

150 TN:UERY INTERESTING! I DIDN'T

KNOW THAT DRAGONS ATE $FOOD.

160 *YONDER

170 T:

180 T:THAT'S ALL FOR NOW. SEE YOU

AROUND.

190 E:

READY
```

Figure 6-2

You can see how this program works in Figures 6-3 and 6-4.



Figure 6-3



Figure 6-4

COMPARISON Numeric Conditions

A YES/NO decision based on comparing two numbers is called a **numeric condition**. For example, if the amount of money in my pocket is equal to, or more than, the price of a hot fudge sundae, I will order the sundae (YES condition); if it is less, I will order something less expensive (NO condition).

There are six possible comparisons you can make between two numbers. In PILOT, you express these comparisons using the following symbols:

#A = #B	#A equals #B
#C < 20	#C is less then 20
#G > #H	#G is greater than #H
#G <> 3	#G is not equal to 3
#L <= 5	#L is less than or equal to 5
#B >= #C	#B is greater than or equal to #C

You can make numeric comparisons between two numeric variables, or between a numeric variable and a constant, and you can make any PILOT command conditional on a numeric comparison. Enclose the comparison in parentheses and place it between the command and the colon (:), like the Y or N in a string match condition. Here are some examples:

J (#G<3): ★ AGAIN	JUMP if the value is $\#G$ is less than 3 to $\#$ AGAIN; otherwise keep going.
T (#A = #B): RIGHT!	Type "Right!" if the value of #A equals the value of #B; otherwise, skip this command.
A(#P<=5):\$ANS	Accept input from the keyboard if #P is less than or equal to 5; otherwise skip this command and keep going.
SO(#N<>#R): 3,7	Sound the tones 3 and 7 if the value of $\#N$ is not equal to the value of $\#R$; otherwise, skip this command.

A common use of numeric conditions is setting up counting loops in programs. Figure 6-5 shows a simple example of how a numeric condition is used to print something repeatedly for a desired number of times.

```
10 R:GOOD BEHAVIOR

20 T:WHAT IS YOUR FULL NAME? \

30 A:$NAME

40 T:HOW MANY TIMES? \

50 A:#T

50 T:* CLEARS THE SCREENJ

70 C:#C=1

80 *REPEAT

90 T(#C(10): \

100 T:#C.I WILL NOT TALK IN CLASS

ANYMORE.

110 C:#C=#C+1

120 J(#C(=#T):*REPEAT

130 T:

140 T:SINCERELY,

150 T:$NAME

160 E:

READY
```



Figure 6-5

Figure 6-6 shows how you can use a numeric condition to limit a person to three guesses in a guessing game.

```
10 R:WHAT AM I?
20 T:WELCOME TO ''WHAT AM I?''
30 T:I'LL GIVE YOU 3 HINTS \
40 T:TO GUESS WHAT I AM . . .
50 PA:60
60 T:
70 T:ARE YOU READY?
80 A:
90 T:
100 M: Y,SURE,OK,FINE,ALRIGHT
110 JN:*GOODBYE
120 C:#G=1
130 *LOOP
 140 T(#G=1) : I ROLL ALONG, BUT I DO
NOT HAVE WHEELS.
150 T(#G=2) :I HAVE A MOUTH, BUT I
CANNOT SPEAK.
 160 T(#G=3) : I HAVE A BED, BUT I
160 T(#G=3) :I HAVE A BED,
NEVER SLEEP.
170 T:WHAT AM I?
180 T:
190 A:$ANSWER
200 M:RIVER,STREAM,CREEK
210 JY:*RIGHT
220 J(#G=3) :*NOMORE
230 T:NOPE, GUESS AGAIN.
240 T:
250 C:#G=#G+1
260 J:*LOOP
270 *NOMORE
280 T:
290 T:NOPE, THAT'S THREE GUESSES.
300 T:I AM A RIVER.
310 J:*GOODBYE
320 *RIGHT
330 T:
340 T:THAT'S CORRECT! I AM
SANSHER.
350 *GOODBYE
360 T:
370 PA:60
380 T:5EE YOU LATER.
390 E:
```



Figure 6-6

READY

JM: Jump on Match

The JM: command causes the computer to jump, conditional on matching one of a list of match alternatives. It is a *variable* jump rather than a constant jump. In the simple J: ***** LABEL command, you always jump to a *single* ***** LABEL. This variable form of the JUMP command lets you jump to one of a variety of ***** LABELS, depending on what matches in an M: command.

The JM: command must be paired with an M: command as follows:

A: M: String1, String2, String3, String4..... JM: * LABEL1, * LABEL2, * LABEL3, * LABEL4.....

The JM: command should have the same number of labels as the M: has strings. The JM: command will jump to the * LABEL in the same position as the first string that matches the accepted input. In other words, if STRING1 is a match, JM: will jump to * LABEL1; if STRING2 is a match, JM: will jump to * LABEL2, and so on. If there is no match, or if the position of a matched string does not correspond to the position of a * LABEL, then the JM: command will be skipped.

Figure 6-7 is an example of the use of the JM: command. The program draws colored boxes on the screen in the size, color, and location of your choice.

10 R:BOXES IN COLOR 20 T:CHOOSE A SIZE, COLOR AND LOCATION. 30 T:THIS PROGRAM DRAWS BOXES ACCORDING TO YOUR CHOICES. 40 T: 50 T:PRESS RETURN TO BEGIN 60 A: 70 GR:CLEAR 80 *LOOP 90 T: 100 T:SIDE LENGTH? \ 110 A:#5 120 T:WHAT COLOR (RED,BLUE, YELLOW,BLACK3? \ 130 A:\$COLOR 140 M: RE, BLU, YE, BLA 150 JM:*RED,*BLU,*YEL,*BLA 150 T:X LOCATION? \ 190 A:#X 200 T:Y LOCATION? \ 210 A:#Y 220 U:*BOX 230 J:*LOOP

```
240 *RED

250 GR:PEN RED

260 J:*CONTINUE

270 *BLU

280 GR:PEN BLUE

290 J:*CONTINUE

300 *YEL

310 GR:PEN YELLOW

320 J:*CONTINUE

330 *BLA

340 GR:PEN ERASE

350 J:*CONTINUE

360 *BOX

370 GR:GOTO #X,#Y

380 GR:TURNTO 90;3CDRAH #S;TURN

903

390 GR:FILL #S

400 E:

READY
```



Figure 6-7

X LOCATION? -30 Y LOCATION? 0 SIDE LENGTH?



APPENDIX A Special Function Keys and Screen Editing

SPECIAL FUNCTION KEYS

Л

ESC

CTRL

CTRL 1

BREAK

CAPS LOWR

A number of keys on the ATARI 400/800[™] Personal Computer System keyboards have a special function or purpose. These functions are described below.

Reverse (Inverse) Video Key, or ATARI Logo Key: Pressing this key causes the text to be reversed on the screen (dark text on light background). Press the key a second time to return to normal text.

Lowercase Key: Pressing this key shifts the screen characters from uppercase (capitals) to lowercase. To restore the characters to uppercase, press the SHIFT key and the CAPS LOWR key simultaneously.

Escape Key: Pressing this key causes a command to be entered into a program for later execution.

Example: To clear the screen, you would enter:

10 T: ESC CTRL CLEAR

This will cause a curved arrow to appear on your screen as follows:

10 T: 7

Control Key: This key is used in conjunction with other keys to print special graphics control characters. See back cover or PILOT Reference Card for the specific keys and their screen-character representations.

Control 1: Holding down **CTRL** and pressing **1** temporarily stops whatever is happening on the screen (e.g., a program listing). Pressing **CTRL 1** again restarts the screen action.

Break Key: Pressing this key during program execution causes execution to stop. The line number and statement where the execution stopped are displayed on the screen followed by ***READY***.

SYSTEM RESET	System Reset Key: Similar to BREAK in that pressing this key stops program execution. Also returns the screen display to the Text mode, clears the screen, and returns margins and other variables to their default values.
SET CLR TAB	Tab Key: Press SHIFT and the SET CLR TAB keys simultaneously to set a tab. To clear a tab, press the CTRL and SET CLR TAB keys simultaneously. Used alone, the SET CLR TAB advances the cursor to the next tab position. In Deferred mode, set and clear tabs by preceding the above with a line number, the command T:, a quotation mark, and pressing the ESC key.
	Examples: 100 T: ESC SHIFT SET CLR TAB 200 T: ESC CTRL SET CLR TAB
	Default tab settings are placed at columns 5, 14, 22, 30, and 38.
DELETE BACK S	Back Space Key: Pressing this key replaces the character to the left of the cursor with a space and moves cursor back one space.
CLEAR	Clear Key: Pressing this key while holding down the SHIFT or CTRL key blanks the screen and puts the cursor in the upper left corner.
RETURN	Return Key : Terminator to indicate an end of a line of PILOT. Pressing this key causes a numbered line to be interpreted and ad- ded to a PILOT program in RAM.
	An unnumbered line (in Immediate mode) is interpreted and ex- ecuted immediately. Any variables are placed in a variable table.

SCREEN EDITING

The keyboard and display are logically combined for a mode of operation known as screen editing. Each time a change is completed on the screen, the RETURN key must be pressed. Otherwise, the change is not made to the program in memory.

Example: 10 T:REMEMBER TO PRESS RETURN 15 T:AFTER LINE EDIT 20 T:THIS LINE IS GOING AWAY 30 T:THIS WILL BE THE FIRST 40 T:LINE ON THE SCREEN, 50 E: To delete line 20 from the program, type the line number and press the **RETURN** key. Merely deleting the line from the screen display does **not** delete it from the program.

In addition to the special function keys described above, there are cursor control, insert, and delete keys that allow immediate editing capabilities. These keys are used in conjunction with the CTRL or SHIFT keys as follows:

CTRL	Moves cursor up one physical line without changing the program or display.
	Moves cursor one space to the right without disturbing the program or display.
	Moves cursor down one physical line without changing the pro- gram or display.
	Moves cursor one space to the left without disturbing the program or display.

Like the other keys on the ATARI keyboard, holding the cursor control keys for more than $\frac{1}{2}$ second causes the keys to repeat.

INSERT	Insert key: Press the SHIFT and SYSTEM RESET keys simultaneously to insert a line. To insert a single character, press the CTRL and INSERT keys simultaneously.
SHIFT INSERT	Inserts one physical line.
CTRL	Inserts one character space.
DELETE BACK S	Delete key: Press the SHIFT and DELETE BACK S keys simultaneously to delete a line. To delete a single character, press CTRL DELETE BACK S simultaneously.
SHIFT DELETE	Deletes one physical line.
CTRL DELETE	Deletes one character or space.

Note: You should not use screen editing features other than Backspace/Delete in AUTO mode. Instead, return to the Immediate mode and LIST your program to use screen editing.

APPENDIX B PILOT I/O Error Codes

This appendix lists the ATARI 400/800 Computer Systems' I/O error codes within the context in which they will be seen in ATARI PILOT. Not all of the system codes are presented here, because some of them cannot occur within the PILOT environment.

130	A nonexistent device was specified.
131	A READ command followed a WRITE command with the same device specified.
135	A WRITE command followed a READ command with the same device specified.
136	End-of-file condition.
138	Device timeout; device doesn't respond. (See Note)
139	Device NAK. (See Note)
140	Serial bus framing error. (See Note)
141	Screen cursor out of range (READ from or WRITE to 'S').
142	Serial bus data from overrun. (See Note)
143	Serial bus data from checksum error. (See Note)
144	Device DONE error. (See Note)
145	Disk read after write compare error. (See Note)
146	Function not implemented for device (e.g., OUT:K).
147	Insufficient RAM for operating the graphics screen.
160	Disk drive number error.
161	Too many concurrent disk files being accessed.
162	Disk is full (no free sectors).
163	Fatal system data I/O error.
164	File number mismatch. (See Note)

- 165 Disk file naming error.
- 167 Disk file locked.
- 169 Disk directory full (64 files).
- 170 Disk file not found in directory.

Note : These errors indicate problems over which the user has no direct control; they are due to hardware problems and should seldom be seen.



LIMITED 90-DAY WARRANTY ON ATARI® PERSONAL COMPUTER PRODUCTS

ATARI, INC. ("ATARI") warrants to the original consumer purchaser that this ATARI Personal Computer Product (not including computer programs) shall be free from any defects in material or workmanship for a period of 90 days from the date of purchase. If any such defect is discovered within the warranty period, ATARI's sole obligation will be to repair or replace, at its election, the Computer Product free of charge on receipt of the unit (charges prepaid, if mailed or shipped) with proof of date of purchase satisfactory to ATARI at any authorized ATARI Service Center. For the location of an authorized ATARI Service Center nearest you, call toll-free:

In California (800) 672-1430 Continental U.S. (800) 538-8547

or write to:

Atari, Inc. Customer Service Department 1340 Bordeaux Drive Sunnyvale, CA 94086

YOU MUST RETURN DEFECTIVE COMPUTER PRODUCTS TO AN AUTHORIZED ATARI SERVICE CENTER FOR IN-WARRANTY REPAIR.

This warranty shall not apply if the Computer Product: (i) has been misused or shows signs of excessive wear, (ii) has been damaged by being used with any products not supplied by ATARI, or (iii) has been damaged by being serviced or modified by anyone other than an authorized ATARI Service Center.

ANY APPLICABLE IMPLIED WARRANTIES, INCLUDING WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PAR-TICULAR PURPOSE, ARE HEREBY LIMITED TO NINETY DAYS FROM THE DATE OF PURCHASE. CONSEQUENTIAL OR IN-CIDENTAL DAMAGES RESULTING FROM A BREACH OF ANY APPLICABLE EXPRESS OR IMPLIED WARRANTIES ARE HEREBY EXCLUDED. Some states do not allow limitations on how long an implied warranty lasts or do not allow the exclusion or limitation of incidental or consequential damages, so the above limitations or exclusions may not apply to you.

This warranty gives you specific legal rights and you may also have other rights which vary from state to state.

DISCLAIMER OF WARRANTY ON ATARI COMPUTER PROGRAMS

All ATARI computer programs are distributed on an "as is" basis without warranty of any kind. The entire risk as to the quality and performance of such programs is with the purchaser. Should the programs prove defective following their purchase, the purchaser and not the manufacturer, distributor, or retailer assumes the entire cost of all necessary servicing or repair.

ATARI shall have no liability or responsibility to a purchaser, customer, or any other person or entity with respect to any liability, loss, or damage caused directly or indirectly by computer programs sold by ATARI. This disclaimer includes but is not limited to any interruption of service, loss of business or anticipatory profits or consequential damages resulting from the use or operation of such computer programs.

REPAIR SERVICE

If your ATARI Personal Computer Product requires repair other than under warranty, please contact your local authorized ATARI Service Center for repair information.

IMPORTANT: If you ship your ATARI Personal Computer Product, package it securely and ship it, charges prepaid and insured, by parcel post or United Parcel Service.

